



MPLAB Code Configurator v3.xx User's Guide

MPLAB® Code Configurator v3.xx User's Guide

Preface

**Important: Notice to customers:**

All documentation becomes dated, and this manual is no exception. Microchip tools and documentation are constantly evolving to meet customer needs, so some actual dialogs and/or tool descriptions may differ from those in this document. Please refer to our website (www.microchip.com) to obtain the latest documentation available.

Documents are identified with a “DS” number. This number is located on the bottom of each page, in front of the page number. The numbering convention for the DS number is “DSXXXXXXXXA”, where “XXXXXXXX” is the document number and “A” is the revision level of the document.

Introduction

This document describes how to install, configure and use the MPLAB® Code Configurator (MCC) software tool before starting or during the development process of an embedded software application designed with PIC® microcontrollers.

Recommended Reading

This user's guide refers to MCC operation only. Other useful documents are listed below. The following Microchip documents are available and recommended as supplemental reference resources:

- Release Notes for the MPLAB Code Configurator
- MPLAB X IDE User's Guide

Table of Contents

Preface.....	1
1. Introduction	3
2. Installation.....	4
2.1. Installing MPLAB Code Configurator from the Microchip Plugins Update Center.....	4
2.2. Installing MPLAB Code Configurator from the Microchip Website.....	5
2.3. Updating MPLAB Code Configurator.....	6
2.4. Older MPLAB Code Configurator Versions.....	6
3. Operating Areas.....	7
3.1. Resource Management Area.....	7
3.2. Versions Area.....	14
3.3. Pin Manager Package View Area.....	15
3.4. Pin Manager Grid View Area.....	16
3.5. The Composer Area.....	19
3.6. MCC Options.....	22
4. Generating MCC Drivers.....	25
4.1. Setting Up MPLAB X IDE and Launching MCC.....	25
4.2. Selecting and Configuring Modules.....	26
4.3. Generating Code.....	27
5. Generated Sources and Header Files.....	30
6. MCC Device Migration.....	32
7. Revision History.....	33
The Microchip Web Site.....	34
Customer Change Notification Service.....	34
Customer Support.....	34
Microchip Devices Code Protection Feature.....	34
Legal Notice.....	35
Trademarks.....	35
Quality Management System Certified by DNV.....	36
Worldwide Sales and Service.....	37

1. Introduction

The MPLAB[®] Code Configurator (MCC) generates driver code using a Graphical User Interface (GUI). The generated drivers control the peripherals on PIC[®] microcontrollers. The GUI provides an easy means for setting up the configuration of the peripherals. MCC is a plugin for the MPLAB[®] X IDE and MPLAB[®] Xpress.

Additionally, the MCC is used to configure and generate libraries, which allows code generation and configuration for software libraries and external components.

The generated drivers or libraries can be used in any Microchip PIC or AVR device application program. MCC requires creating or opening an already existing project in the MPLAB X IDE or MPLAB Xpress, before launching the MCC plugin. This is necessary as the MCC needs to know the device used in the project, to have access to device-specific information like registers, bits and configurations, and to set up the MCC GUI.

The MCC generates source and header files based on selections made in the GUI. The generated files are added to the active project of MPLAB X IDE or MPLAB Xpress.

2. Installation


The MPLAB Code Configurator can be installed in two ways: via the Microchip Plugins Update Center, or from the Microchip website. The following chapters describe these procedures and also the MCC update process.

2.1 Installing MPLAB Code Configurator from the Microchip Plugins Update Center

By default, MCC is not installed together with the MPLAB X IDE and must be downloaded separately and installed. One way to do so is via the Microchip Plugins Update Center:

1. In the MPLAB X IDE, go to **Tools -> Plugins**.
2. Go to the **Available Plugins** tab.
3. Select MPLAB Code Configurator and click the **Install** button. See figure below.
4. The Plugin installer opens. Click **Next** and check the Terms and Agreements. After this step, the Plugin installer begins downloading the MCC plugin.
5. When the MCC plugin download is complete, MPLAB X IDE will ask to be restarted. Upon restart, the plugin is installed.
6. MCC can now be opened on a new or already existing MPLAB X IDE project. See [Section 4.1 "Setting Up MPLAB X IDE and Launching MCC."](#)

Figure 2-1. Installing MPLAB Code Configurator



2.2 Installing MPLAB Code Configurator from the Microchip Website

The MCC plugin can also be downloaded from the Microchip website by typing the address www.microchip.com/mcc in a web browser, selecting the **Current Download** tab and downloading the Current Version .zip file. See [Figure 2-2](#).


Figure 2-2. Downloading MCC from the Microchip Website

Features Current Download Archive Download Documentation				
Current Version				
Title	Version	Date Published	Release Notes	D/L
MPLAB® Code Configurator	3.45.1	12/1/2017		

Once downloaded, extract the archive which contains the MCC plugin to a preferred location. To install the downloaded plugin, complete the following instructions:

1. Open MPLAB X IDE.
2. Go to **Tools -> Plugins**.
3. Select the **Downloaded** tab and click on the **Add Plugins...** button.
4. Navigate to the folder where the downloaded .zip file was extracted and select the MCC plugin. It should have a .nbm file extension.
5. Click on the **Install** button. MPLAB X IDE will ask to be restarted. Upon restart, the plugin is installed. See figure below.
6. MCC can now be opened on a new or already existing MPLAB X IDE project. See [Section 4.1 "Setting Up MPLAB X IDE and Launching MCC."](#)


Figure 2-3. Installing MCC from Downloaded File



2.3 Updating MPLAB Code Configurator

When a MCC version newer than the one installed is available, the MPLAB X IDE will display a notification in the bottom right corner of the IDE window. By clicking on it, the plugin update wizard is launched. In the wizard, simply click on the **Install** button, which will download and install the new MCC plugin version. See figure below.

Figure 2-4. Updating MPLAB Code Configurator



2.4 Older MPLAB Code Configurator Versions


Older MCC versions are available at the same www.microchip.com/mcc address, under the **Archive Download** tab.

3. Operating Areas

The MCC user interface consists of six main operating areas, as shown in [Figure 3-1](#).

1. **Resource Management Area:** contains the Project Resources and all the available/device resources. See [3.1 Resource Management Area](#) section for more details.
2. **Versions Area:** shows the complete list of MCC Cores, Peripheral Libraries and Software Libraries which can be used with the selected device. Some of these are installed together with MCC, others are available for download. Depending on the selected device, some core and library versions are interchangeable. See [3.2 Versions Area](#) section for more details.
3. **Pin Manager Package View Area:** graphic interface for pin selection and configuration. Bidirectional operation with the Pin Manager Grid View. See [3.3 Pin Manager Package View Area](#) section for more details.
4. **Pin Manager Grid View Area:** contains three inner tabs: Notifications (errors, warnings and general information regarding the current selections), Pin Manager - Grid View (a table version of the Pin Module Package View) and Output (MCC Log & MPLAB X IDE Log). See [3.4 Pin Manager Grid View Area](#) chapter for more details.
5. **Composer Area:** this is the main area in which a peripheral or library driver can be configured. It displays the possible configurations of the peripheral/library. See [3.5 The Composer Area](#) chapter for more details.

Figure 3-1. MCC Operating Areas



Note: All operating areas are dockable. Each can be dragged and dropped into another position, even out of the MPLAB X IDE main window (closing the IDE however will close all MCC windows, including the ones moved outside the IDE).



3.1 Resource Management Area

The Resource Management Area comes with two separate views: the tree view and the flat view. Both provide access to the complete list of software/peripheral components and the components selected for the current project configuration. For more details on each view, please refer to [3.1.1 Resource Management Area - Tree View](#) and [3.1.2 Resource Management Area - Flat View](#) sections.

The Project Resources section is common to both views of the Resource Management Area. This section displays the list of on-chip peripherals, external components and libraries that have been selected for the current MCC project. The information specific to each of the two views regarding this section is available in [3.1.1 Resource Management Area - Tree View](#) and [3.1.2 Resource Management Area - Flat View](#) sections.

There are three system modules that are always available in the Project Resources section. These modules cannot be removed. The modules are:


1. **Interrupt Module:** configures the interrupts for the device.
2. **Pin Module:** configures the pins for the device.
3. **System Module:** configures the system clock, Configuration bits, and other device-level functions for the device.

A module in the Project Resources window can be removed from the project by clicking the  or  button to the right of the module name in the Project Resources section. The module will be removed from the MPLAB X IDE project. When a module is removed from the Project Resources, all of the unsaved configuration information for that module is lost.

At the top of the Project Resources section, there are three buttons:


- **Generate:** once the project configuration has been completed, clicking this button will trigger the code generation process for that specific configuration.
- **Import:** an MCC configuration file (.mcc3 extension) can be imported into the current project. If the selected configuration has been created for a device other than the one used in the current project, an alert message pops up offering the possibility of an experimental configuration migration. Once a configuration file is selected, MCC loads and configures all modules detailed in the selected configuration file. If there is a match between a module from the configuration and a module already loaded in the current project, the settings for the loaded module is overwritten with the ones from the imported configuration file. This is useful for the partial configurations created manually or provided by the Export functionality detailed below. In the case of importing a configuration created for a different device than the one used in the current project, an alert message pops up offering the possibility of an experimental configuration migration or canceling the import process (See [Figure 3-2](#)). During device migration the import process might fail due to hardware mismatches between the two devices, in which case a backup configuration file is created and saved in the project folder. (See [Section 6 "MCC Device Migration"](#)).

Figure 3-2. Importing a Configuration Created for a Different Device



- **Export:** allows the export of partial configurations. Any loaded module in the Project Resources, except System modules, can be selected for a partial configuration by right-clicking on the module and selecting "**Mark for config export**" (see figure below for more details). All modules marked for export are shown in bold. Clicking the **Export** button creates an MCC configuration consisting only of the modules marked for export. To remove selection use "Unmark from config export" for a specific module or "Unmark all for config export" for all modules/components selected for export.

Figure 3-3. The Context Menu of the Project Resources Area



Besides the partial configuration export mechanism, the Context menu of the Project Resources Area (displayed above) includes several other operations on the loaded components or modules, such as:

- **Force Update:** regenerates code for all the selected modules/components, even if there were no modifications added to their configuration. See [Section 4.3 "Generating Code"](#).
- **Refresh [module_name] Windows:** reopens the configuration window of the selected module if that window has been closed previously. If the Context menu is invoked by right-clicking under the Resources list, with no module/component selected, this option will be available as Refresh Module Windows and its effect will be global - all previously closed MCC windows will be reopened.
- **[module_name] Help:** opens the help content for the user interface of the selected module/component, if available.


3.1.1 Resource Management Area - Tree View

This view is further split into the Projects Resources section (detailed at the beginning of [3.1 Resource Management Area](#) chapter) and the Device Resources section. See [Figure 3-4](#).

Both sections in the Tree View can also be navigated and handled by using the following keys:


- **Up and down arrow keys:** for moving up and down in the tree, respectively
- **Right arrow key:** for expanding a node
- **Left arrow key:** for collapsing a node

Figure 3-4. Resource Management Area - Tree View



3.1.1.1 The Project Resources section

This section displays the peripherals, libraries or external components selected for the current project. The selection is done via the Device Resources section. The System Module, Pin Module and Interrupt Module are selected by default. The configuration for each of the selected modules is done through the Composer Area. The peripheral and libraries are added to the project by selecting them from the Device Resources section. To add a peripheral or library to the Project Resources section, double-click on its name in the Device Resources section. The configuration can then be done via the corresponding GUI in the Composer Area. A module in the Project Resources window can be removed from the project by

clicking the  button to the right of the module name in the Project Resources section. The module will be removed from the MPLAB X IDE project. When a module is removed from the Project Resources, all of the unsaved configuration information for that module is lost.

3.1.1.2 The Device Resources section


The Device Resources section (see figure below) lists data sheet, external components and libraries available for the device configured in the MPLAB X IDE project, based on the loaded libraries in the Versions area.. When the name of a peripheral or library is double-clicked, it is moved from the Device Resources area to the Project Resources area, simultaneously invoking the Pin Manager with all associated I/O pins.

Note: The Documents section of the Device Resources area provides a link to the data sheet of the selected device on <http://www.microchip.com>.

Right-clicking on a module or component in this tree shows the Device Resources context menu through which the help content of the selected module can be invoked. The Device Resources list can be filtered via the top combo box (see figure below). The available filters are:

- all supported and tested modules
- all supported modules (including untested ones)
- all modules (including unsupported ones)


Figure 3-5. Resource Filtering in Device Resources - Tree View



3.1.2 Resource Management Area - Flat View


This view is further split into the Projects Resources section (detailed at the beginning of [3.1 Resource Management Area](#) chapter) and the available resources section. See figure below.



Figure 3-6. Resource Management Area - Flat View



3.1.2.1 The Project Resources section

This section displays the peripherals, libraries or external components selected for the current project. Selection is done via the Available Resources window which can be accessed from the Available Resources section (see [3.1.2.2 The Available Resources section](#)). The Project Resources section in the Flat View is similar to the Project Resources in the Tree View (see [3.1.1.1 The Project Resources section](#)). A module in the Project Resources section in the Flat View can be removed from the project by

clicking the  button to the right of the module name. The module will be removed from the MPLAB X IDE project. When a module is removed from the Project Resources, all the unsaved configuration





























































information for that module is lost. Next to the  button, the  button offers insight about a specific selected module. The same module information can be retrieved from the [module_name] Help option in the Project Resources context menu (see [Figure 3-3](#) figure).

3.1.2.2 The Available Resources section



This section contains two buttons:

- **Show [device_name] Product Page:** opens the product page from the Microchip website in the default browser.
- **Show Available Resources:** opens, or brings into focus, the Available Resources window in the Composer Area. See the [Figure 3-7](#) figure below.

Figure 3-7. Available Resources Window


Start Page MPLAB X Store Available Resources Pin Module System Module Interrupt Module...		
Module	Type	Library
 4-20mA R	  Interface	Available Libraries
 4-20mA T	  Interface	Clear All Libraries
 Accel3	  Sensors	✓ 8-bit Bootloader Library
 ACcurrent	  Mixed-Signal	✓ AVR-IoT WG Sensor Node
 ADC	  Peripheral	✓ Foundation Services Library
 ADC	  Mixed-Signal	✓ LIN Library
 ADC2	  Mixed-Signal	✓ MikroElektronika Click Library
 ADC3	  Mixed-Signal	✓ PIC10 / PIC12 / PIC16 / PIC18 MCUs
 AirQuality	  Sensors	✓ UCS211X
 Alcohol	  Sensors	✓ mTouch Capacitive Sensing Library
 Altitude	  Sensors	MikroElektronika Click Library
 Ammeter	  Mixed-Signal	MikroElektronika Click Library
 AT	  Peripheral	PIC10 / PIC12 / PIC16 / PIC18 MCUs
 AudioAmp	  Audio and Voice	MikroElektronika Click Library
 AVR-IoT WG Sensor Node	  Examples	AVR-IoT WG Sensor Node
 BLE2	  Wireless Connectivity	MikroElektronika Click Library
 Bluetooth	  Wireless Connectivity	MikroElektronika Click Library
 BluetoothAudio	  Wireless Connectivity	MikroElektronika Click Library
 Bootloader Generator	  Bootloader Generator	8-bit Bootloader Library
 CAN SPI	  Interface	MikroElektronika Click Library

The Available Resources window in the Composer Area represents a table of all software/peripheral components available for the selected device with search and filter capabilities. Each module in this table is indexed by three attributes: module name, module type and the library containing the module. These attributes are mapped on each table column as follows:

- Module:** displays the module icon, module name, link to module help (via the  button and module selection (via the  button). When a module is selected, it is added to the Project Resources section under the Resources Management area. A module can be searched by its name using the text field in the Module column header. The Available Resources table can be sorted alphabetically by module name when clicking on the arrow in the column header.
- Type:** displays the type of functionality provided by each module (i.e. Peripheral, Interface, Mixed-Signal). The table entries can be filtered by module type using the text field in the Type column header. The Available Resources table can be sorted alphabetically by module type when clicking on the arrow in the column header.
- Library:** shows the name of the library containing a certain module. The table entries can be filtered using the Available Libraries drop-down in the Library column header. Using the Available Libraries drop-down, the table contents can be filtered to include modules from one or several libraries. Also, it is possible to show modules from all libraries (using the All Libraries option) or clear the whole table (using the Clear All Libraries option). The Available Resources table can be sorted alphabetically by

library name when clicking on the arrow in the column header. Depending on the selected device and the selected filters, the Available Resources window might show several modules with the same name but coming from different libraries. For example, in the case detailed in the [Figure 3-7](#) figure there are two ADC modules shown: one from the peripheral library and the other from the MikroElektronika Clicks library. Generally, modules bearing the same name are mutually exclusive. After a module selection, no other module with the same name can be selected. The module selection button becomes grayed out and clicking on it will yield a pop-up message saying that the operation cannot be completed (see the [Figure 3-8](#) figure).

Figure 3-8. Module selection disabled



3.2 Versions Area


The Versions Area provides information about the versions of each MCC Core, Peripheral Library, Software Library or other component installed on the local machine. Over time, multiple versions of the libraries may be available. MCC can be configured to use a specific version of a Library for the current MCC project.

Loaded versions are displayed with a green check mark, compatible but not loaded versions are displayed with a grey circle, and available versions which are unsupported by the selected core version are displayed with a circle backslash symbol (see [Figure 3-9](#)).

The MCC Core versions can be switched by right-clicking on an available core version and selecting "Switch core version" from the Context menu. Library versions can be loaded by right-clicking on a version of a component/module and selecting "Mark For Load." This action triggers the **Load Selected Library** button to appear at the top of the Versions Area. By clicking the button, all library versions which have been marked are loaded into MCC. Multiple selection is allowed; several components can be loaded at the same time. Only one version for each module/component is allowed to be loaded at a time.

If the component is already installed on the local machine, the absolute path to the corresponding .jar file is displayed next to the component name. If the component has not yet been installed, the "Available for download" message is displayed instead. Selecting an uninstalled component for load and then pressing the **Load Selected Libraries** button will download the corresponding .jar file from a Microchip server and will subsequently load it in MCC, provided that the selected version is compatible with the loaded core version.

Figure 3-9. Versions Area



Besides the Versions Area, a core or a library can be loaded also via the MPLABX IDE menu in **Tools** → **Options** → **Plugins** → **MPLAB Code Configurator** (see [Section 3.8 “MCC Options”](#)).

Note: All MCC libraries are published via the Microchip website: www.microchip.com/mcc.

3.3 Pin Manager Package View Area


The following color combinations are associated with the pins in Graphical or Table View:

1. **Gray colored pin:** the pin is not usable in the selected configuration and there is no enabled module which has any functionality on that pin. There are also grayed out locks on a white background that indicate pins that are locked out by selected system functions.
2. **Blue colored pin:** pins that are available to be allocated to a module.
3. **Green colored pin (with a lock):** the pin has been allocated and selected for a module. The name displayed against the pin is either the name of the pin in the module's context or a custom name entered.
4. **Green colored pin (with chain link):** the pin is shared between multiple functions.
5. **Yellow colored pin:** a possible alternate pin for an already allocated pin function.
6. **Grayed out locks on a white background:** pins that are locked out by selected system functions.

The graphical Pin Manager can be zoomed in and out in order to adjust its visibility. This can be done by scrolling the mouse wheel when the mouse is over the Package View. Zooming can also be achieved by the “+” and “-” keys on the keyboard (useful if the mouse is not available).

By right-clicking on a specific pin, all available pin functions are listed for selection. A snapshot of the package view configuration can be saved in PNG format by right-clicking on the package and selecting "Export Image."

Figure 3-10. Package View Area



3.4 Pin Manager Grid View Area

This area contains three inner tabs: Pin Manager Grid View, Output and Notifications.

3.4.1 The Pin Manager Grid View

In the Pin Manager Grid View, the device package can be selected from a drop-down list. The package selection is in the upper left side of the Pin Manager Table View. In the figure below, the drop-down list shows that the QFN64 package has been selected. The selected package will be displayed in the Package View. The pin numbers in the Table View will also show the pin numbers for the selected package.

Figure 3-11. The Grid View Area

[illegible]

The three leftmost columns in the Table View indicate the module's name, functionality name and the direction, respectively.

The Table View allows to:

- Expand/collapse rows and ports ([Figure 3-12](#))
- Hide and show ports and rows ([Figure 3-13](#) and [Figure 3-14](#))
- Show only the pins that are configured (Isolate) ([Figure 3-15](#))

Figure 3-12. Collapsing Ports and Rows

[illegible]

Figure 3-13. Hiding Ports and Rows

Module	Function	Direction
	CLC1OUT	output
CLC1	Isolate Selected Pins	input
	Show All	input
ICD	Hide Row	input
	PGDX	input

MPLAB Code Configurator v3.xx User'...

Operating Areas

Figure 3-14. Restoring Ports and Rows (Show All)





Figure 3-15. Isolating the Selected Pins



3.4.2 The MPLAB Code Configurator - Output Tab

This tab displays the MCC operation results (see figure below). The MPLAB X IDE Log is also displayed under the **Output** tab when specifically opened from the **View -> IDE Log** menu.

Figure 3-16. The MPLAB Code Configurator - Output Tab



3.4.3 The Notifications Tab

During the configuration process, several messages may be displayed in the **Notifications** tab (Figure 3-15) to help identify issues or simply in order to make sure a specific setting is configured as intended. These are indexed in the **Notifications** tab by:





1. **Category:** identifies the notification as an alert or information that the module depends on another module.
2. **Module Name:** is the name of the module that generated the notification.
3. **Type:** indicates the severity of the notification.

There are four types of notifications:

- **SEVERE:** either the code generation or the compilation process will be faulty with the current configuration.
- **WARNING:** the code will be generated according to settings made and it may compile, but it might also fail to function as intended.
- **HINT:** this provides information to assist in the successful configuration of the module. The module and the MCC can still be used. Action might be required.
- **INFO:** information only, no action is required.

These can be filtered out using the Type combo box. If there are any WARNING or SEVERE type messages present in the **Notifications** tab when the **Generate** button is clicked, a message box displays, giving the option of reconfiguration in order to eliminate the possible errors in the current settings. This action can be skipped, assuming the notifications have been reviewed and taken into consideration.

Figure 3-17. The Notifications Tab

Output - MPLAB® Code Configurator		Notifications [MCC]	Pin Manager: Grid View	
Category	Module Name	Type:	ALL	Description
	ADCC	HINT	Display SEVERE and above	Selected Tad (128.0 us) > maximumTad (6.0 us). Please higher the sampling frequency!
	CCP1	INFO	Display WARNING and above	The CCP1 module uses Timer 2
	CCP1	WARNING	Display HINT and above	In order to use the PWM mode, please configure Timer 2 to use Fosc/4 as clock source.
	DSM	HINT	Display INFO and above	Enable CLC1 module
			Display all levels	

Note: The notification type may change as the MCC configuration changes. For example, WARNING might indicate that a module requires another module to be added to the project to operate correctly. After the module is added, the notification type would change to INFO.

3.5 The Composer Area

When a peripheral, library or other external component is selected from the Project Resources Area, its corresponding configuration GUI is displayed in the Composer Area. The Composer Area ([Figure 3-18](#)) is where peripherals and libraries are configured based on the application's requirements.

3.5.1 The Easy Setup Tab

Figure 3-18. The Easy Setup Tab of the PIC16F1947 EUSART Module

The screenshot shows the 'EUSART1' configuration window in the MPLAB Code Configurator. The 'Easy Setup' tab is selected. Under 'Hardware Settings', the 'Mode' is set to 'asynchronous'. The 'Enable EUSART' checkbox is checked, and the 'Baud Rate' is set to 9600 with an error of 0.160%. Other options like 'Enable Transmit', 'Enable Wake-up', 'Auto-Baud Detection', 'Enable Address Detect', and 'Enable Receive' are unchecked. The 'Transmission Bits' and 'Reception Bits' are both set to 8-bit, and the 'Data Polarity' is set to Non-Inverted. Under 'Software Settings', the 'Redirect STDIO to USART' checkbox is unchecked, and both the 'Software Transmit Buffer Size' and 'Software Receive Buffer Size' are set to 8.

The EUSART **Easy Setup** tab in the Composer Area allows configuring various EUSART parameters related to transmission and reception operations.

3.5.2 The Registers Tab

In addition to the **Easy Setup** tab in the module's Composer, MCC also provides a **Registers** tab ([Figure 3-19](#)). The **Registers** tab provides direct access to configure the module's registers and settings, providing unrestricted access to the configuration of the module.

Any module configuration done using the **Easy Setup** tab will be reflected in the values displayed in the **Registers** tab. Likewise, changes performed in the **Registers** tab will be reflected in the values in the **Easy Setup** tab.

Figure 3-19. The Register View

▼ EUSART1

Interrupt Enables

☐ TXI

☐ RCI

▶ Register: BAUD1CON

▶ Register: RC1STA

▶ Register: SP1BRGH

▶ Register: SP1BRGL

▶ Register: TX1REG

▼ Register: TX1STA

BRGH ▼

CSRC ▼

SENDB ▼

SYNC ▼

TRMT ▼

TX9 ▼

TX9D

TXEN ▼

3.5.3 The Pin Module Tab

For any pin which has been configured in the Pin Manager Table View, additional configuration of that pin can be done using the Pin Module View in the Composer Area. To display the Pin Module View, click on the **Pin Module** tab in the Project Resources Area (see [Figure 3-20.](#))

The following settings are available in this tab (depending on the selected pin).

- **Pin Name:** the port pin name
- **Module:** the name of the module containing the function of the pin.
- **Function:** module-specific functionality available on the pin. A pin may have one or more selectable functions. Typically, a pin may be configured to have several functions at the same time if it is also configured as an input (Output column unchecked). Only one function per each pin can be matched with an output direction. Please refer to the device data sheet for more details.

- **Custom Name:** a useful pin alias which can be used in the generated code. A set of macros are made available in the Pin Module generated code for each selected pin in MCC.
- **Start High:** sets the pin to a high/low logic level at device initialization.
- **Analog:** configures the pin as analog or digital.
- **Output:** sets the pin direction of the pin.
- **WPU:** enables the weak pull-up resistor on the pin.
- **WPD:** enables the weak pull-down resistor on the pin.
- **OD:** enables the open-drain capability on the pin.
- **IOC:** configures the interrupt-on-change capability of the pin.

Note: Some of the settings detailed above may be missing on some pins or from the device completely. Please refer to the pins configuration section in the device data sheet.

Figure 3-20. The Pin Module Tab

Pin Module System Module Interrupt Module EUSART1 ADC

Pin Module

Easy Setup Registers


Selected Package : QFN64

Pin Name ▲	Module	Function	Custom Name	Start High	Analog	Output	WPU	OD	IOC
RA0	ADC	AN0	channel_AN0	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>			
RA1	ADC	AN1	channel_AN1	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>			
RB2	Pin Module	GPIO	IO_RB2	<input checked="" type="checkbox"/>		<input type="checkbox"/>	<input checked="" type="checkbox"/>		any ▼
RB4	Pin Module	GPIO	IO_RB4	<input type="checkbox"/>		<input checked="" type="checkbox"/>	<input type="checkbox"/>		positive ▼
RC6	EUSART1	TX1		<input type="checkbox"/>		<input checked="" type="checkbox"/>			
RC7	EUSART1	RX1		<input type="checkbox"/>		<input type="checkbox"/>			

3.6 MCC Options

Several aspects of the operation of the MCC can be managed by using the “Options” panel (see figure below), which can be invoked by clicking **Tools** → **Options** → **Plugins** → **MPLAB Code Configurator** in the menu bar of the MPLAB X IDE.

Figure 3-21. The MCC Option Panel



The MCC Options panel offers the following controls:

- [File Handling](#)
- [Generated Line Endings](#)
- [Editor Behavior](#)

3.6.1 File Handling

1. **Remove unused files from the project:** enabling this option tells the MCC to remove .c and .h files for modules which were removed from the MCC configuration between the subsequent generation procedures. This option ensures that the files which are included in the project (and thus in the compilation) are only those which are strictly necessary. However, this will not delete the files from the disk.
2. **Delete unused files from the disk:** this option gets enabled only when selecting “Remove unused files from the project.” This performs the additional task of deleting unused files from the disk. Once a file is deleted, it cannot be recovered.

3.6.2 MCC Line Endings

Specify the type of line endings to use in the files generated by MCC. The default is DOS (<CR><LF>). Unix line endings (<LF>) may be specified.

3.6.3 Editor Behavior

1. **Always ask before removing a module:** enabling this control enables the “Are you sure?” dialog box which appears while disabling or removing an enabled module.
2. **Always ask before removing a pin:** enabling this control enables the “Are you sure?” dialog box which appears while deallocating or removing a pin from a peripheral.

3.6.4 Installing a MPLAB Code Configurator Library

The MPLAB Code Configurator provides a peripheral or software library installation feature. This feature can be used to add the MCC-compatible libraries. There are several libraries for various applications the user can choose from on the <http://www.microchip.com/mcc> webpage. An MCC Library file should have a `.jar` or a `.mc3lib` file extension. Once this file is downloaded, open the MPLAB X IDE and in the above menu go to **Tools** → **Options** → **Plugins** → **MPLAB Code Configurator 3.x**, click on the **Install Library** button and select the `.jar` file via the **Open File** dialog box. The Versions window will now list the newly added library as installed.

If there are multiple versions of a library, the newly installed one will not be the loaded one. To load a particular version of a library, right-click on it and select “Mark for Load,” which will then highlight the user’s choice. If the user has multiple libraries with multiple versions in each, one from each can be highlighted before loading them. See [Section 3.3. “Versions Area”](#) for more details about switching library versions.

Removing a library is done using the **Remove Library** button. The File selection dialogue window will open the **Library** folder. Select the library to remove and click on the **Remove** button on the File selection dialogue. The library can be verified if it is no longer present anymore on the machine by going to the [Versions operating area](#) - the removed library version is not present on the machine anymore. It may be present as available for download.

If a library currently in use is attempted to be removed (green tick in the Versions area), MCC will not allow this to happen. In order to remove that library version, switch to another version, go back to the Options window and press the **Remove Library** button again for the library version to delete.

3.6.5 Installing a MPLAB Code Configurator Core

The MPLAB Code Configurator provides a core switching feature. This feature works simultaneously on various projects with different core versions without uninstalling or reinstalling the plugin. In order to install a new core, download first the new core from the Microchip MCC webpage (<http://www.microchip.com/mcc>). This file should have a `.mc3core` file extension. Once this file is downloaded, open the MPLAB X IDE and in the above menu go to **Tools** → **Options** → **Plugins** → **MPLAB Code Configurator 3.x**, click on the **Install Core** button and select the `.mc3core` file via the **Open File** dialog box. The Versions window will now list the fresh core installation.

To switch to another core version, either double click on it, or right-click on it and select “Switch Core Version.” The Versions window will now refresh the core selection with the user’s choice. The core installations can always be checked by opening the **Core** folder, from **Tools** → **Options** → **Plugins** → **MPLAB Code Configurator 3.x** path. Refer to [Section 3.4. “Versions Area”](#) for more details about core switching.

Removing a core version is done from the **Remove Core** button. The Folder selection dialogue window will open the “Core” folder. Select the core version to remove and click on the **Remove** button on the Folder selection dialogue. The core version can be verified it is no longer present on the machine anymore by going to the [Versions operating area](#) - the core version removed is not present on the machine anymore. It may be present as available for download.

If a core version currently in use is attempted to be removed (green tick in the Versions area), MCC will not allow this to happen. In order to remove that core version, switch to another core version, go back to the Options window and press the **Remove Core** button again for the core version to delete.

4. Generating MCC Drivers

Now that MCC has been installed and its main operating areas were learned, it's time to set up MCC according to the user's needs and begin configuring the project. The following subsections cover basic MCC operation and the code generation process.


4.1 Setting Up MPLAB X IDE and Launching MCC

To generate drivers using the MCC in MPLAB X IDE, follow these steps:

1. Create a new MPLAB X IDE project or open an existing project (see figure below).
2. If multiple projects are open in MPLAB X IDE, set one as the main (active) project by selecting "Set as Main Project" in the MPLAB X IDE. For the active project, the MCC automatically includes the generated driver files.
3. Open the MCC plugin tool. In the menu bar of the MPLAB X IDE, go to **Tools** → **Embedded** → **MPLAB Code Configurator 3.x: Open/Close**. Or click on the MCC icon in the MPLAB X IDE toolbar.

Note: For MAC users, the "Embedded" selection will be under the Preferences menu. This launches the MCC GUI.

Figure 4-1. Opening the MCC in MPLAB X IDE



When opening MCC for the first time on an MPLAB X project, the configuration saving dialog will be displayed asking for a name and saving path for the MCC configuration file attached to the project. The MCC configuration is also saved to the disk when the **Generate** button is pressed, or if the MPLAB X IDE **Save** button is clicked. An existing MCC configuration file can be loaded by double-clicking on the desired `.mc3` file in the **Important Files** section of the MPLAB X IDE project.

4.2 Selecting and Configuring Modules

After opening the MCC, the peripheral and library modules can be added to the project.

1. In the Project Resource Area, click the name of the peripheral or library module which needs to be configured. After a peripheral or library module is selected, the configuration GUI for that peripheral is displayed in the Composer Area.
2. Configure the peripheral as required by the application in the Composer Area.
3. Configure the pins in the Pin Manager Area depending upon the application requirements.

4.3 Generating Code

When the MCC **Generate** button is pressed in the Project Resources window, the listed actions are performed by MCC. Details of the code generation are shown in the MCC **Output** tab. See [3.4.2 The MPLAB Code Configurator - Output Tab](#).

1. The MCC configuration file is saved.
2. MCC generates code for the peripheral or library module if the module's configuration has changed since the last time MCC generated code for that module.

Note: All modules can be forced to be generated by MCC by right-clicking in the Project Resources section from the [3.1 Resource Management Area](#) and selecting "Force Update," before clicking on the **Generate** button.

If MCC attempts to regenerate a file on the disk that has been modified outside of MCC, the **Merge [MCC]** window is displayed. Use the **Merge [MCC]** window to select whether to keep the modified file (default action), or to replace the modified content with the content generated by MCC.

The **Merge [MCC]** window is discussed in [Section 4.3.2 "The Merge \[MCC\] Window."](#)

4.3.1 Saving and Loading the MCC Configuration

Saving and loading the MCC configuration is integrated into the MPLAB X IDE Save and Load functions. The MCC configuration is saved whenever the **Generate** button is pressed. The MCC configuration can also be saved by clicking on the MPLAB X IDE Save tool, or selecting **Save** from the File menu.

The MCC configuration file is included in the MPLAB X IDE project, under the **Important Files** folder. The configuration file uses the extension `.mc3`. Double-clicking on the MCC configuration file will cause that MCC configuration to be loaded.

4.3.2 The Merge [MCC] Window

If any of the files generated by the MCC have been edited outside of MCC and saved to the disk, then the **Merge [MCC]** window appears in the Composer Area. Use the **Merge [MCC]** window to select whether to keep the edits, or to replace them with the MCC newly generated code.

Note: The user's edits will never be overwritten by the MCC generated code, except by explicit action in the **Merge [MCC]** window.


When changes have been made both to a generated file and also in the corresponding MCC UI within the Composer Area, the **Merge [MCC]** window shown in [Figure 4-2](#) will be displayed. The **Merge [MCC]** window allows to resolve the conflicts between the newly generated file and the edits made to the file.

When the newly generated MCC content has been accepted, MCC makes the changes to the file. To the MPLAB X IDE, these changes are the same as if they were typed in the new content. The normal MPLAB X IDE edit undo can be used in the MCC Merge operation.

MPLAB Code Configurator v3.xx User'...

Generating MCC Drivers


Figure 4-2. Merge [MCC] Window - File List



A list of all the files that need to be merged is shown at the top of the **Merge [MCC]** window. Each file in the list must be selected, in turn, to ensure that all of the newly generated code is incorporated into the project.

At the top of the **Merge [MCC]** window, in the center margin, there is an arrow, as shown in Figure 4-3. Clicking on the arrow will replace all the edits in the current file with the MCC updated code that the MCC has just generated. The numbers above the arrow indicate the current difference and the total number of differences.

Figure 4-3. Merge [MCC] Window - Replacing All Edits with MCC Generated Code




MPLAB Code Configurator v3.xx User'...

Generating MCC Drivers

The individual lines of **MCC Updated Code** can be selected to replace the edited code. As shown in [Figure 4-4](#), clicking on the arrows in the right margin of the left window will copy the **MCC Updated Code** to the generated driver file. Once the changes are accepted, the Merge mechanism will remove the highlighted file and highlight the next file on the list. To insure all updates are completed, a warning will be generated if the Merge mechanism is closed before all the changes are accepted.

Figure 4-4. Merge [MCC] Window - Replacing Single Changes with MCC Generated Code




Note:

1. Remember to merge the code for every file shown in the file list of the **Merge [MCC]** window.
2. Be sure to save all the changed files from the Merge process.

5. Generated Sources and Header Files

The generated drivers will be included in the active MPLAB X IDE project, as shown in the figure below.

Figure 5-1. Generated Source and Header Files



1. The `mcc.h` and `mcc.c` files include the definitions of Configuration bits and the 'OSCILLATOR_initializer' function. These definitions are based on the settings which were made for the System module in the Composer. Also included is the 'SYSTEM_initializer' function which can be called in the application program to call all the other default initializers (the ones marked in the GUI by sprocket symbol).
2. The `pin_manager.h` and `pin_manager.c` files include the Pin Manager initializer functions based on the configurations which were made in the Pin Manager GUI.
3. The `interrupt_manager.h` and `interrupt_manager.c` files are optional files which are generated only when peripheral interrupts are enabled and they include interrupt initializer functions.
4. The `.c` and `.h` are module specific files and include each module's peripheral/library configuration functions.
5. The `main.c` file is generated only when the MCC detects that there is no `main.c` file present in the project. If there is any previous `main.c` in the project regardless of its creator (the user or the

MCC), it will not generate or overwrite the existing one. When using a `main.c` not generated by the MCC, the lines `#include "mcc_generated_files/mcc.h";` and `SYSTEM_Initializer()` need to be added to the `main.c` file. The `main.c` file generated by the MCC may include commented out code lines to enable interrupts. Remove the comments from the appropriate lines if the application requires interrupts to be enabled when it starts.

The functions provided in any of these MCC generated files can be called from the user application code, as required. The MPLAB X IDE provides auto-completion assistance of all of the MCC generated content. While editing source code in the project, start typing in a MCC API, or MCC variable name, and press **<CTRL+ Space>**. The MPLAB X IDE will show a list of options to complete the entry.

6. MCC Device Migration

Using a MCC configuration created for one device, on a different device is called MCC device migration.

Note: MCC device migration is not supported in MCC.

It is possible that attempting to use a MCC configuration on a device other than the one for which it was created, might appear not to fail. It is entirely the user's responsibility to determine if the MCC code generated as the result of device migration is suitable for use in their application.

Unintended MCC device migration may occur if the selected device in the MPLAB X IDE project is changed after MCC has been configured for that project. Copying a MCC configuration file (*.mcc3) to another MPLAB X IDE project may also cause MCC device migration or other unintended operation.

7. Revision History

Revision A (January 2016)

Initial release of the document.

Revision B (May 2016)

Revise Figure 1-1; Revise Chapter 2; Revised Figure 2-5 Title; Add Figures 2-6 through 2-10; Revise Chapter 3.

Revision C (May 2018)

Added Chapter 2 Installation; updated text in Chapter 3 Operating Areas; removed previous Figures 1-1, 2-8, 2-13, 2-16, 2-17, 2-18 and 2-19; changed or replaced various figures; added Figures 3-3, 3-4, 3-6, added text in Chapter 3 in Project Resources Area and Versions Area; moved text to Package View Area; added subchapter 3.5.3. The Notification Tab; subchapter 3.6.3 The Pin Module Tab; subchapter 3.7.4 Installing a MPLAB Code Configurator Library; subchapter 3.7.5 Installing a MPLAB Code Configurator Core and different text corrections throughout the document.

Revision D (March 2019)

Updated Chapter 3 content.

The Microchip Web Site

Microchip provides online support via our web site at <http://www.microchip.com/>. This web site is used as a means to make files and information easily available to customers. Accessible by using your favorite Internet browser, the web site contains the following information:

- **Product Support** – Data sheets and errata, application notes and sample programs, design resources, user's guides and hardware support documents, latest software releases and archived software
- **General Technical Support** – Frequently Asked Questions (FAQ), technical support requests, online discussion groups, Microchip consultant program member listing
- **Business of Microchip** – Product selector and ordering guides, latest Microchip press releases, listing of seminars and events, listings of Microchip sales offices, distributors and factory representatives

Customer Change Notification Service

Microchip's customer notification service helps keep customers current on Microchip products. Subscribers will receive e-mail notification whenever there are changes, updates, revisions or errata related to a specified product family or development tool of interest.

To register, access the Microchip web site at <http://www.microchip.com/>. Under "Support", click on "Customer Change Notification" and follow the registration instructions.

Customer Support

Users of Microchip products can receive assistance through several channels:

- Distributor or Representative
- Local Sales Office
- Field Application Engineer (FAE)
- Technical Support

Customers should contact their distributor, representative or Field Application Engineer (FAE) for support. Local sales offices are also available to help customers. A listing of sales offices and locations is included in the back of this document.

Technical support is available through the web site at: <http://www.microchip.com/support>

Microchip Devices Code Protection Feature

Note the following details of the code protection feature on Microchip devices:

- Microchip products meet the specification contained in their particular Microchip Data Sheet.
- Microchip believes that its family of products is one of the most secure families of its kind on the market today, when used in the intended manner and under normal conditions.
- There are dishonest and possibly illegal methods used to breach the code protection feature. All of these methods, to our knowledge, require using the Microchip products in a manner outside the operating specifications contained in Microchip's Data Sheets. Most likely, the person doing so is engaged in theft of intellectual property.
- Microchip is willing to work with the customer who is concerned about the integrity of their code.

- Neither Microchip nor any other semiconductor manufacturer can guarantee the security of their code. Code protection does not mean that we are guaranteeing the product as “unbreakable.”

Code protection is constantly evolving. We at Microchip are committed to continuously improving the code protection features of our products. Attempts to break Microchip's code protection feature may be a violation of the Digital Millennium Copyright Act. If such acts allow unauthorized access to your software or other copyrighted work, you may have a right to sue for relief under that Act.

Legal Notice

Information contained in this publication regarding device applications and the like is provided only for your convenience and may be superseded by updates. It is your responsibility to ensure that your application meets with your specifications. MICROCHIP MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WHETHER EXPRESS OR IMPLIED, WRITTEN OR ORAL, STATUTORY OR OTHERWISE, RELATED TO THE INFORMATION, INCLUDING BUT NOT LIMITED TO ITS CONDITION, QUALITY, PERFORMANCE, MERCHANTABILITY OR FITNESS FOR PURPOSE. Microchip disclaims all liability arising from this information and its use. Use of Microchip devices in life support and/or safety applications is entirely at the buyer's risk, and the buyer agrees to defend, indemnify and hold harmless Microchip from any and all damages, claims, suits, or expenses resulting from such use. No licenses are conveyed, implicitly or otherwise, under any Microchip intellectual property rights unless otherwise stated.

Trademarks

The Microchip name and logo, the Microchip logo, AnyRate, AVR, AVR logo, AVR Freaks, BeaconThings, BitCloud, CryptoMemory, CryptoRF, dsPIC, FlashFlex, flexPWR, Helder, JukeBlox, KeeLoq, KeeLoq logo, Kleer, LANCheck, LINK MD, maXStylus, maXTouch, MediaLB, megaAVR, MOST, MOST logo, MPLAB, OptoLyzer, PIC, picoPower, PICSTART, PIC32 logo, Prochip Designer, QTouch, RightTouch, SAM-BA, SpyNIC, SST, SST Logo, SuperFlash, tinyAVR, UNI/O, and XMEGA are registered trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

ClockWorks, The Embedded Control Solutions Company, EtherSynch, Hyper Speed Control, HyperLight Load, IntelliMOS, mTouch, Precision Edge, and Quiet-Wire are registered trademarks of Microchip Technology Incorporated in the U.S.A.

Adjacent Key Suppression, AKS, Analog-for-the-Digital Age, Any Capacitor, AnyIn, AnyOut, BodyCom, chipKIT, chipKIT logo, CodeGuard, CryptoAuthentication, CryptoCompanion, CryptoController, dsPICDEM, dsPICDEM.net, Dynamic Average Matching, DAM, ECAN, EtherGREEN, In-Circuit Serial Programming, ICSP, Inter-Chip Connectivity, JitterBlocker, KleerNet, KleerNet logo, Mindi, MiWi, motorBench, MPASM, MPF, MPLAB Certified logo, MPLIB, MPLINK, MultiTRAK, NetDetach, Omniscient Code Generation, PICDEM, PICDEM.net, PICkit, PICtail, PureSilicon, QMatrix, RightTouch logo, REAL ICE, Ripple Blocker, SAM-ICE, Serial Quad I/O, SMART-I.S., SQI, SuperSwitcher, SuperSwitcher II, Total Endurance, TSHARC, USBCheck, VariSense, ViewSpan, WiperLock, Wireless DNA, and ZENA are trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

SQTP is a service mark of Microchip Technology Incorporated in the U.S.A.

Silicon Storage Technology is a registered trademark of Microchip Technology Inc. in other countries.

GestIC is a registered trademark of Microchip Technology Germany II GmbH & Co. KG, a subsidiary of Microchip Technology Inc., in other countries.

All other trademarks mentioned herein are property of their respective companies.

© 2018, Microchip Technology Incorporated, Printed in the U.S.A., All Rights Reserved.

ISBN: 978-1-5224-4245-5

Quality Management System Certified by DNV

ISO/TS 16949

Microchip received ISO/TS-16949:2009 certification for its worldwide headquarters, design and wafer fabrication facilities in Chandler and Tempe, Arizona; Gresham, Oregon and design centers in California and India. The Company's quality system processes and procedures are for its PIC[®] MCUs and dsPIC[®] DSCs, KEELOQ[®] code hopping devices, Serial EEPROMs, microperipherals, nonvolatile memory and analog products. In addition, Microchip's quality system for the design and manufacture of development systems is ISO 9001:2000 certified.

Worldwide Sales and Service

AMERICAS	ASIA/PACIFIC	ASIA/PACIFIC	EUROPE
Corporate Office 2355 West Chandler Blvd. Chandler, AZ 85224-6199 Tel: 480-792-7200 Fax: 480-792-7277 Technical Support: http://www.microchip.com/support Web Address: www.microchip.com	Australia - Sydney Tel: 61-2-9868-6733 China - Beijing Tel: 86-10-8569-7000 China - Chengdu Tel: 86-28-8665-5511 China - Chongqing Tel: 86-23-8980-9588 China - Dongguan Tel: 86-769-8702-9880 China - Guangzhou Tel: 86-20-8755-8029 China - Hangzhou Tel: 86-571-8792-8115 China - Hong Kong SAR Tel: 852-2943-5100 China - Nanjing Tel: 86-25-8473-2460 China - Qingdao Tel: 86-532-8502-7355 China - Shanghai Tel: 86-21-3326-8000 China - Shenyang Tel: 86-24-2334-2829 China - Shenzhen Tel: 86-755-8864-2200 China - Suzhou Tel: 86-186-6233-1526 China - Wuhan Tel: 86-27-5980-5300 China - Xian Tel: 86-29-8833-7252 China - Xiamen Tel: 86-592-2388138 China - Zhuhai Tel: 86-756-3210040	India - Bangalore Tel: 91-80-3090-4444 India - New Delhi Tel: 91-11-4160-8631 India - Pune Tel: 91-20-4121-0141 Japan - Osaka Tel: 81-6-6152-7160 Japan - Tokyo Tel: 81-3-6880-3770 Korea - Daegu Tel: 82-53-744-4301 Korea - Seoul Tel: 82-2-554-7200 Malaysia - Kuala Lumpur Tel: 60-3-7651-7906 Malaysia - Penang Tel: 60-4-227-8870 Philippines - Manila Tel: 63-2-634-9065 Singapore Tel: 65-6334-8870 Taiwan - Hsin Chu Tel: 886-3-577-8366 Taiwan - Kaohsiung Tel: 886-7-213-7830 Taiwan - Taipei Tel: 886-2-2508-8600 Thailand - Bangkok Tel: 66-2-694-1351 Vietnam - Ho Chi Minh Tel: 84-28-5448-2100	Austria - Wels Tel: 43-7242-2244-39 Fax: 43-7242-2244-393 Denmark - Copenhagen Tel: 45-4450-2828 Fax: 45-4485-2829 Finland - Espoo Tel: 358-9-4520-820 France - Paris Tel: 33-1-69-53-63-20 Fax: 33-1-69-30-90-79 Germany - Garching Tel: 49-8931-9700 Germany - Haan Tel: 49-2129-3766400 Germany - Heilbronn Tel: 49-7131-67-3636 Germany - Karlsruhe Tel: 49-721-625370 Germany - Munich Tel: 49-89-627-144-0 Fax: 49-89-627-144-44 Germany - Rosenheim Tel: 49-8031-354-560 Israel - Ra'anana Tel: 972-9-744-7705 Italy - Milan Tel: 39-0331-742611 Fax: 39-0331-466781 Italy - Padova Tel: 39-049-7625286 Netherlands - Drunen Tel: 31-416-690399 Fax: 31-416-690340 Norway - Trondheim Tel: 47-7289-7561 Poland - Warsaw Tel: 48-22-3325737 Romania - Bucharest Tel: 40-21-407-87-50 Spain - Madrid Tel: 34-91-708-08-90 Fax: 34-91-708-08-91 Sweden - Gothenberg Tel: 46-31-704-60-40 Sweden - Stockholm Tel: 46-8-5090-4654 UK - Wokingham Tel: 44-118-921-5800 Fax: 44-118-921-5820